

REVISE MEASUREMENT/UPDATE POM ASSOCIATION

1. Fill in new measurement in the REVISED (REV) column of the measurement section. Then, click Save.

| Points of Measure | | | | Sample Specification | | | | | | | | |
|-------------------|-------------------------|--------|--------|----------------------|-------------------|------------------|---------------------|-------------------|------------------|---------------------|--------|-------------|
| Code | POM Description | Tol(-) | Tol(+) | Spec | Measurer 1 Actual | Measurer 1 Delta | Measurer 1 Comments | Measurer 2 Actual | Measurer 2 Delta | Measurer 2 Comments | Rev | Modified By |
| A122 | MINIMUM HEAD STRETCH | 0 | 0 | 25 | | | | | | | | TK80063 |
| A300 | *LGTH HPS TO HEM- FRONT | -1/2 | 1/2 | 29 | 29 | 0 | | | | | 28 1/2 | TK80063 |

2. The revised measurement needs to be pushed back to the POM page. To do so, click More Actions > Update POM Association **OR** click the hot key at the top.

Fit Evaluation: 108143

Overview Attachments Change Tracking 4

Fit Evaluation Designer Overview

Initiate Sample Update POM Association Multi Window View Style POM Association Sample Tag

Fit Evaluation Designer Information

Parent Information

| | | | | | |
|-----------------|------------------------|-------------------|----------|--------------|--------------|
| Style No | ONEPLM MANUAL TEMPLATE | Request No | 00615768 | Description | ONEPLM MANUA |
| Fiscal Season | FA20 | Brand | TEKGEAR | Division | MENS |
| Dept | | Development Stage | TEMPLATE | Style Status | NEW |
| Est. In DC Date | | Actual Qty | | | |

More Actions...
 Initiate Sample
 Update POM Associ...
 Delete POM Code(s)
 Apply Sort
 Delete Active Sample
 Add to Favorites
 Multi Window
 Delete Page

3. The new measurement will now be reflected on the POM page.

| Sort | QA | P/S | HTM | Code | POM Description | Tol(-) | Tol(+) | Size Code | 000 | 00 | 0 | 2 | 4 | 6 | 8 | [10] | 12 | 14 | 16 | 18 | 20 |
|--------------------------|----|-----|-----|------|-----------------|--------|--------|-----------|--------|------|--------|-----|--------|--------|---|------|----|----|----|----|----|
| <input type="checkbox"/> | | | | A300 | LEN HPS TO HEM | -1/2 | 1/2 | Grading | -1 | -1/2 | 0 | 1/2 | 1 | 1 1/4 | | | | | | | |
| | | | | | | | | Spec Meas | 27 1/2 | 28 | 28 1/2 | 29 | 29 1/2 | 29 3/4 | | | | | | | |

4. **WARNING:** If you have more than one FIT EVAL tied to a POM page and revise a spec on the fit eval and push it to the POM page, the revised spec will not push to all the other fit evals. You will need to open each fit eval and individually update the revised specs to match back to the POM page.

Fit Evaluation List

| Fit Eval Id | POM Page Description | Size | Fit Sample |
|-------------|----------------------|------|------------|
| 167858 | FIT EVAL 1 | 10 | Sample 1 |
| 167859 | FIT EVAL 2 | 10 | Sample 1 |